



GMC Radiation Monitor

Local radiation monitoring for compatible GQ GMC Geiger counters

User manual
Version 9.1.0
July 2026 edition

Important safety notice

The app is a monitoring, analysis and home-automation tool. It does not replace a calibrated radiation-protection instrument, an official measurement or a professional risk assessment. Unusual or persistently high readings require the measurement setup, device and environment to be checked and, where appropriate, competent authorities or specialists to be consulted.

Measurement	CPM; derived $\mu\text{Sv/h}$ only with an appropriate factor
Storage	Local SQLite database
Long-term windows	24 h, 7 d, 30 d, 90 d, 365 d
Languages	German, English, Spanish, French, Croatian, Italian, Dutch, Polish

Contents

1. Purpose and system overview	3
2. Installation and first start	3
3. Navigation and information levels	4
4. Live measurements, alerts and data quality	4
5. Long-term analysis: windows and background	5
6. Cumulative dose and development over time	5
7. Advanced statistics	6
8. Environmental, event and intervention analysis	6
9. Multi-device comparison and agreement	7
10. Reports, exports and GMCMap	7
11. Backup, restore and deletion	8
12. Configuration and maintenance	8
13. Troubleshooting and scientific limits	9

The app is a monitoring, analysis and home-automation tool. It does not replace a calibrated radiation-protection instrument, an official measurement or a professional risk assessment. Unusual or persistently high readings require the measurement setup, device and environment to be checked and, where appropriate, competent authorities or specialists to be consulted.

1. Purpose and system overview

- GMC Radiation Monitor reads compatible GQ GMC Geiger counters locally over USB serial, stores confirmed measurements in SQLite and publishes Home Assistant entities through MQTT Discovery.
- The interface separates live status, analysis and expert information. The new long-term analysis complements the existing real-time alerts, adaptive background and multi-device analysis without duplicating them.
- Measurements, reports and backups remain local. External transfer occurs only through explicitly enabled functions such as GMCTMap.

2. Installation and first start

- Install the app from the Home Assistant app repository, verify that MQTT is available and start the app after saving the device configuration.
- Give every counter a unique name and, where possible, bind it to its serial number. Select the correct detector profile; custom conversion factors should have a documented source.
- Open the web interface and check device status, data age, CPM, dose rate and stored history. A newly connected device may need a short synchronisation period.

3. Navigation and information levels

- Summary shows the essential live values, connection states, warnings and plain-language conclusions.
- Analysis shows background comparison, trends, long-term windows, events, environmental context and device comparisons.
- Expert view shows raw-data quality, detector factors, dead-time correction, statistical diagnostics and technical protocol information.
- Collapsible groups prevent overload. On small screens, wide tables scroll inside their card while the page itself remains free of horizontal overflow.

4. Live measurements, alerts and data quality

- CPM is the primary count rate. A $\mu\text{Sv/h}$ value is a device- and detector-dependent derivation and is only as reliable as the conversion factor and calibration.
- Absolute alarm thresholds and smart notifications remain separate from long-term statistics. Statistical signals never alter radiation-safety thresholds.
- Unconfirmed isolated spikes are not stored as confirmed history. Quality flags, gaps, timestamps and device availability remain traceable.
- With multiple devices, each counter is monitored independently; one offline device does not set the others offline.

5. Long-term analysis: windows and background

- The app calculates real 24-hour, 7-day, 30-day, 90-day and 365-day windows rather than merely taking the last N records.
- A number is shown only when duration and minimum coverage are sufficient. Otherwise the card states “Not yet meaningful” and explains why.
- Missing values are not interpolated. Mean, median, quantiles and coverage use only existing accepted measurements.
- A robust local background is calculated per device and context. Connected relative elevations are grouped into episodes with start, duration, mean, maximum and excess area.

6. Cumulative dose and development over time

- Cumulative dose is integrated from stored dose-rate values. It is a derived estimate, not personal dosimetry.
- An annual projection is shown only from a sufficiently long and complete basis and is clearly labelled as a projection.
- Daily and monthly values, calendar heat map, rolling seven-day median and month-of-year profile reveal long-term development. The seasonal profile requires at least six represented calendar months.
- Changes in location, geometry, detector, firmware or calibration can influence long-term patterns and must be considered.

7. Advanced statistics

- Effective sample size accounts for temporal dependence between consecutive measurements.
- Moving-block bootstrap provides robust confidence intervals for time-dependent data. Mann-Kendall and Sen slope describe monotonic trends without assuming normality.
- EWMA and CUSUM can reveal small sustained level shifts. Overdispersion describes variability beyond a simple count model.
- These methods provide context only. They do not identify a radiation source or prove a cause.

8. Environmental, event and intervention analysis

- Optional Home Assistant temperature and pressure sensors can be linked to the radiation series.
- Lagged Spearman associations are explored at 0, 3, 6, 12 and 24 hours. Correlation does not imply causation.
- Event annotations document moves, weather events, building changes or checks. They appear in reports and support before/after review.
- Comparisons should use equivalent device, location, detector and timing conditions wherever possible.

9. Multi-device comparison and agreement

- The existing fleet view compares time-paired values and shows shared rises, relative calibration, drift and position changes.
- Bland-Altman bias and 95% limits of agreement complement correlation. High correlation alone does not demonstrate agreement.
- Comparisons between different tubes or conversion factors must remain device-specific. CPM and $\mu\text{Sv/h}$ are not interchangeable without evidence.
- Unusual differences should be checked with parallel measurements, setup documentation and calibration records.

10. Reports, exports and GMCMap

- Reports can be generated by device, period and display mode. CSV and JSON support further analysis; PDF reports document results and limitations.
- Long series are peak-preservingly reduced for charts while statistics and data exports continue to use the relevant full dataset.
- GMCMap is optional. Enable upload only after privacy confirmation and enter the account and device-specific counter ID correctly.
- A GMCMap upload is not a replacement for local storage or a scientific archive.

11. Backup, restore and deletion

- Managed SQLite backups and full exports protect the history. Test backups and retain important copies outside the Home Assistant system.
- Restore and complete deletion are disabled by default. Enable `history_management_enabled` only for planned maintenance and disable it afterwards.
- Restores are checked for schema and SQLite integrity before data are merged. Deletion requires explicit text confirmation and is protected server-side.
- Home Assistant Recorder history and the local app database are separate storage areas.

12. Configuration and maintenance

- Important groups are devices, GMCMap, history, analysis, safety, interface and system. Change only parameters whose effect is understood.
- For annual windows, retention must be at least 365 days; new installations default to 730 days.
- After updates, verify the displayed version, device assignments, conversion factors, MQTT entities and report language.
- Review diagnostics and logs for location, serial-number and account information before sharing them.

13. Troubleshooting and scientific limits

- No connection: check USB assignment, cable, model, startup delay and app log. Use diagnostics for fragmented serial replies instead of arbitrarily shortening timing values.
- No long-term values: check duration, coverage, retention and device filters.
- Implausible dose rate: check detector profile, CPM-per- $\mu\text{Sv/h}$ factor, dead-time model and calibration reference.
- Statistical sophistication cannot replace calibration, suitable placement or knowledge of energy response. Radiation-protection decisions require competent expertise.

Important safety notice

The app is a monitoring, analysis and home-automation tool. It does not replace a calibrated radiation-protection instrument, an official measurement or a professional risk assessment. Unusual or persistently high readings require the measurement setup, device and environment to be checked and, where appropriate, competent authorities or specialists to be consulted.